
Origami corner bookmark


Cream = reverse face. Green = outer face. Keep one orientation until the page-fitting step.

STEP 1 - Put the reverse face upward




Start with a square and point one corner toward you. The cream face is upward here; green is the other face. Keep the sheet flat.

STEP 2 - Fold the bottom corner to the top




Bring the point nearest you to the far point. Align those corners, then press along the long bottom fold. The green face is now visible.

STEP 3 - Make the left guide fold



Bring the left point up to the top point. Press the sloping fold from the left edge midpoint to the middle of the long bottom edge.

STEP 4 - Make the right guide fold




Bring the right point up to that same top point. The two flaps meet down the middle, forming a smaller square held like a diamond.

Origami corner bookmark

Cream = reverse face. Green = outer face. Keep one orientation until the page-fitting step.


STEP 5 - Open the right guide fold



Open the right flap

Return the right flap to its original side point. Keep the first diagonal fold closed and leave the new sloping crease in place.


STEP 6 - Open the left guide fold



Back to the broad triangle

Open the left flap too. You have the broad triangle again, with two sloping guide creases. Do not unfold the long bottom edge.


STEP 7 - Find the front sheet



Layers separated to show the front sheet

At the upper point, gently separate the two sheets. Keep the rear point standing. Hold only the point on the sheet facing you.

STEP 8 - Lower only the front point



Front tip meets the base midpoint


Keep the rear tip up

Fold that front point down to the middle of the long bottom edge. Press the short horizontal fold. The rear point stays at the top; the cream folded flap makes the front of the pocket.

Origami corner bookmark

Cream = reverse face. Green = outer face. Keep one orientation until the page-fitting step.


STEP 9 - Raise the left side again



Left flap up; right side still open

Refold the left point to the top using its existing sloping crease. Leave the right side open for now. The upper part of this raised flap is the part to tuck.

STEP 10 - Tuck the left tip inside




Left tip goes behind the pocket flap

Dashed arrow: hidden inside

Lift the horizontal pocket lip slightly. Bend the raised left tip downward and feed it behind the cream pocket flap, toward the bottom point. Press the side fold; do not push through the rear sheet.


STEP 11 - Raise the right side



Right flap to the top

Refold the right point to the top along its guide crease. Keep the first tucked flap inside its pocket while moving this side.

STEP 12 - Tuck the right tip inside




Right tip tucks into the same pocket

Lift the same pocket lip and fold the right tip down into the remaining half of the pocket. Settle both flaps without pulling the first one out.

Origami corner bookmark

Cream = reverse face. Green = outer face. Keep one orientation until the page-fitting step.

STEP 13 - Flatten and find the opening




Both tips hidden inside

A square held like a diamond

Press the sloping side folds and the center seam gently. Leave the straight pocket opening between the front triangle and the back square free to open. Both tips should be hidden inside.

STEP 14 - Slide in one page corner



One page goes between the layers

Rotate the bookmark to match the page corner. Guide that single corner through the mouth, behind the green front triangle. Ease it toward the closed corner, then stop when it sits comfortably.

Before decorating: both side tips are hidden inside.

The pocket mouth remains free to open.


Try one ordinary page; stop if it drags or buckles.

Fit-to-page printing is fine. These diagrams are not a cutting template.

Origami corner bookmark


Close-up reminders: a separated layer, the tuck opening and the page between the two faces.

Front sheet only



Move only the front point downward

Tip inside the pocket




Tip goes between these two layers

Close-up of the opening; not a new fold

One page between the front and back

Side view: one page inside



Gap enlarged to show the layers

Start with a square of thin paper. A 15 cm starting side gives a nominal 7.5 cm finished square before allowing for paper thickness. The fit must be checked with your chosen paper and book.